

This page is part of the [mios_c_simulator_-_debugger](#)

[ACSim_console.h](#)

[ACSim_console.c](#)

[ACSim_mios.h](#)

[ACSim_mios.c](#)

[ACSim_toolbox.h](#)

[ACSim_toolbox.c](#)

[ACMidiDefines.h](#)

1

```
/*
 * ACSim_toolbox.c
 * v 0.0.5
 *
 * 2006 April 17 Created by Michael Markert, audiocommander.de
 * Copyright 2006 Michael Markert, http://www.audiocommander.de
 * hexview based on publicdomain code:
http://www.eggdrop.ch/texts/cschnipsel/
 * toolbox for mios: http://www.midibox.org
 *
 */

/*
 * Released under GNU General Public License
 * http://www.gnu.org/licenses/gpl.html
 *
 * This program is free software; you can redistribute it and/or modify
it under the terms
 * of the GNU General Public License as published by the Free Software
Foundation
 *
 * YOU ARE ALLOWED TO COPY AND CHANGE
 * BUT YOU MUST RELEASE THE SOURCE TOO (UNDER GNU GPL) IF YOU RELEASE
YOUR PRODUCT
 * YOU ARE NOT ALLOWED NOT USE IT WITHIN PROPRIETARY CLOSED-SOURCE
PROJECTS
 */

#import "ACSim_toolbox.h"

#import "ACSim_console.h"
```

```
// generate some random numbers
unsigned char ACRandomBool(void) { return (random() % 2); }
signed char ACRandomEncoder(void) { return ((random() % 2) ? -1 :
1 ); }
unsigned char ACRandomPin(void) { return (random() %
DEBUG_AIN_NUM); }
unsigned char ACRandomChar(void) { return (random() % 128); }
unsigned int ACRandomInt(void) { return (random() % 1024); }

// hexview output
// maybe configure defines in header!

void hexview(unsigned char *buf, int size) {
    /* usage:
    char buf[256];
    strcpy(buf, "some data");
    hexview(buf, sizeof(buf)); */

    int i;
    unsigned char c;
    unsigned char r = 0;

    while (size>0) {
        printf("%i:\t\t", (r*16));
        for (i=0; i<HEXVIEW_CHARS; i++) {
            if (size-i>0) {
                printf("%02x ", (unsigned char)*(buf+i));
            } else {
                printf(" ");
            }
        }
        printf(" ");
        for (i=0; i<HEXVIEW_CHARS&&size-i>0; i++) {
            c = (unsigned char)*(buf+i);
            printf("%c", c>=32&&c<127 ? c : '.');
        }
        buf+=HEXVIEW_CHARS;
        size-=HEXVIEW_CHARS;
        printf("\n");
        r++;
    }
}
```

From:
<https://www.midibox.org/dokuwiki/> - **MIDIbox**

Permanent link:
https://www.midibox.org/dokuwiki/doku.php?id=acsim_toolbox_c&rev=1187734549

Last update: **2007/09/30 06:36**

